

 **HOLO**LIGHT
STREAM

Hololight Stream Client for Spectacles

Contents

1. Objectives	3
2. Prerequisites	3
3. Hololight Stream Client for Spectacles	3
3.1. Set up Spectacles to use Hololight Stream	3
3.1.1. Set up the Hololight Stream utility for Spectacles	4
3.1.2. Check if Spectacles are set up to use Hololight Stream	7
3.1.3. Set up Spectacles to use Hololight Stream	8
3.1.4. Set up Wi-Fi connection settings on the Spectacles	9
3.2. Connect to a Hololight Stream application with Spectacles	10
3.3. Disconnect from a Hololight Stream application with Spectacles	11

1. Objectives

- Set up a Spectacles device to use Hologlight Stream Client.
- Use Spectacles to connect to and disconnect from a Hologlight Stream-based application.

2. Prerequisites

- PC using a Windows operating system
- Spectacles from Snap Inc. device
For more information on Spectacles, check out the [Snap Inc. page on Spectacles](#).
- USB-C charging cable to connect Spectacles to a PC

3. Hologlight Stream Client for Spectacles

Unlike other Hologlight Stream-supported devices, you can't download or sideload Hologlight Stream Client to Spectacles. Instead you need to use the Hologlight Stream utility for Spectacles to connect the device to Hologlight Stream applications.


3.1. Set up Spectacles to use Hologlight Stream

Using the Hologlight Stream utility for Spectacles you can quickly get Spectacles ready to use Hologlight Stream, but first you need to set up your Spectacles device.


3.1.1. Set up the Hololight Stream utility for Spectacles

Before you can set up Spectacles, you first need to set up the Hololight Stream utility for Spectacles on a PC.

1. Using a Windows-based PC, open **hololight_stream_utility_spectacles_2025.0.exe**.
2. Select and mark the checkbox next to **I agree to the license terms and conditions**.




3. Select where you want shortcuts to the application to appear. Then select **Install**.



NOTE

You may receive a prompt asking, "Do you want to allow public and private networks to access this app?" Allowing this gives Android Debug Bridge (adb.exe) access to the internet through your firewall. This is optional and will not impact the Hologlight Stream utility for Spectacles.

- The installation process will take a moment. When the process is complete, you can check the box next to **Run the Hololight Stream utility for Spectacles** if you are ready to continue and then select **Finish** to leave the installer.




3.1.2. Check if Spectacles are set up to use Hologlight Stream


Your Spectacles device might already be set up to work with Hologlight Stream. You can check whether the device was previously set up to work with Hologlight Stream using the Hologlight Stream utility for Spectacles.

1. Using the Hologlight Stream utility for Spectacles, select **Connection** from the menu on the left side if it isn't already selected.
2. Connect your Spectacles device to the PC running the Hologlight Stream utility for Spectacles. Select **Refresh**.

If you connected the device correctly, the name of the device should appear under **Connection > Device details > Device name**.



3. Check **Connection > Device details > Setup status**. If there is a green circle here, your Spectacles device already has Hololight Stream Client set up. If there is a red circle, you need to still set up your Spectacles device before you can connect them to a Hololight Stream-supported application.



3.1.3. Set up Spectacles to use Hololight Stream

If Spectacles isn't yet set up to use Hololight Stream, this is easy to do with the Hololight Stream utility for Spectacles.

1. Using the Hololight Stream utility for Spectacles, select **Connection** from the menu on the left side if it isn't already selected.
2. Connect your Spectacles to the PC running the Hololight Snap Spectacles Utility Tool. Select **Refresh**. If you connected the device correctly, the name of the device should appear under **Connection > Device details > Device name**.
3. Select **Setup** from the menu on the left side.
4. Select **Set up**.
5. When the set up process is complete, a green circle will appear under **Setup > Set up device > Setup status**.


3.1.4. Set up Wi-Fi connection settings on the Spectacles

Hololight Stream only works if the client device (in this case the Spectacles device) and the Hololight Stream application server are connected to the same network. With Spectacles now configured to use Hololight Stream, you need to use the Hololight Stream utility for Spectacles to connect it to the network you want to use for your Hololight Stream session.

1. Using the Hololight Stream utility for Spectacles, select **Setup** from the menu on the left side if it isn't already selected.
2. Under **Setup > Wi-Fi connection configuration > Network name**, enter the name of the Wi-Fi network you want to connect to. Under **Network password** enter the password for that network.
3. Select **Save**.

If you did everything correctly, a "Connected" indicator will appear under "Wi-Fi connection configuration".


You can also select **Connection** from the menu on the left side and check under **Device details > Wi-Fi status**. You should see a green circle and the name of the network if you successfully set everything up.



3.2. Connect to a Hologlight Stream application with Spectacles

To use Spectacles to connect to and use a Hologlight Stream-based application, you need to start the connection between the two using the Hologlight Stream utility for Spectacles.

1. On the PC you are using to run your Hologlight Stream-supported application, open the application.
2. On the PC with the Hologlight Stream utility for Spectacles, open the utility.
3. Using a compatible cable, connect Spectacles to the PC running the Hologlight Stream utility for Spectacles.
4. Using the Hologlight Stream utility for Spectacles, select **Connection** from the menu on the left side.
5. Under **Hologlight Stream connection > IP address**, enter the IP address for the PC running the Hologlight Stream-supported application.
6. Select **Connect**.



You can now use the application using Spectacles.

3.3. Disconnect from a Hologlight Stream application with Spectacles

If you are connected to a Hologlight Stream-supported application with Spectacles and you want to disconnect, use the Hologlight Stream utility for Spectacles and select **Connection > Hologlight Stream connection > Disconnect**.

